

Geomet

Universal CMM Software

Installation Instructions

Summer 2005 Version 6.65 Release



CMMs
Made in USA
Since 1973



Niagara Falls
New York
www.hemel.com

Welcome to the Geomet Installation Guide

Geomet provides a self-installation program that handles the installation, upgrade and repair tools for your system. When installing Geomet Version 6, you are first required to install DirectX, Microsoft's Multi-Media enhancement to Windows. Geomet now utilizes multi-media tools such as sounds and picture display. The installation program checks for DirectX, and will install the enhancement automatically.

NOTE: These instructions are for full installations, not for Interim Releases.

Installation Programs and Procedures

- Un-Install Previous Version
- Installing DirectX
- Installing Geomet
- Installing Adobe Acrobat Reader
- Installing the ProCounter II USB Interface
- Installing the Rainbow Sentinel Driver (required for Windows XP / 2000)
- Upgrading the PMAC PC104 CMM Interface
- Installing and Calibrating Helmel Joystick Controls
- CMM Interface Selection

Geomet self configures to many computer and interface versions of old and new Geomet systems. This is accomplished through the use of a CMM interface software module, commonly referred to as a Table Controller. When installing Geomet for the first time, Geomet will prompt you to select an interface, *see Table Controller Identification Table*. Once this has been established, Geomet will continue loading and records the interface selected for future use.

When updating Geomet, you are first recommended to un-install previous versions. See the Un-Install Previous Version section.

Limitations: The DirectX enhancement to Windows works with Windows 98, Windows XP and Windows 2000 versions of Geomet.

NOTE: Windows 95 is no longer supported with Geomet version 6.00.002.xxx and newer. If your Geomet system is installed on a Windows 95 system, it is suggested that you upgrade your operating system. You can obtain Windows upgrade packages directly from Microsoft and many local vendors in your area. Geomet Version 6.00.001 and previous versions will still operate on Windows 95 systems.

Technical Support for installations can be found on the Geomet Web Site at:
<http://www.geomet-cmm-software.com/knowledg.htm>

Hemel Engineering Products, Inc.

6520 Lockport Road

Niagara Falls, NY 14305

(716) 297-8644 • (716) 297-9405 fax

www.hemel.com • www.geomet-cmm-software.com

Installing Geomet

To install Geomet, place the CD in your system's drive. This CD contains an auto run option and will start the installation of Geomet automatically. For other products such as GeoStat or GeoCAD, run the setup.exe file under the appropriate directory of the Geomet CD.

The installation starts with a quick review of the Readme.pdf latest instructions. Should your system currently not have Adobe Acrobat Reader, see installing the Acrobat Reader on 2-6.

To start Geomet installation, open the folder Geomet and double click on the file setup.exe. The setup routine will launch and guide you through the steps required.



figure 3, CD Contents

Step 1 - Welcome to the Installer

This first step is the welcome screen for the installer, press <Next> to proceed, see figure 4.



figure 4, Welcome Screen



figure 5, License Screen

Step 2 - License Agreement

This step requires that you have read and agreed to the terms and conditions with regard to using Geomet, see figure 5.

Step 3 - Customer Information

Complete the required fields as shown in figure 6.



figure 6, Customer Information



figure 7, Select Interface Type

Step 4 - Select CMM Interface Type

Choose the CMM Interface type, see figure 7. This will determine the method of communication between the Geomet software and the physical CMM. See the CMM Interface on the Geomet Module Security Code sheet. Highlight the correct Interface type, and press <Next>.

Step 5 - Custom Setup Box

The Custom Setup screen allows advanced users to customize the Geomet installation. Press the <Install> button to continue.

Step 6 - Accept and Begin

The final step, when accepted by pressing the <Install> button, will begin the installation of Geomet to your system. Installation also installs the files necessary for the un-install process.

Once completed, the installer will notify you of the success of the installation process. Should any errors occur, you will be notified. The most common error noted has been leaving Geomet active while attempting to upgrade. This will cause an error and the installation

TableCtrl Name	Interface Type	Communication Port	CMM / Joystick Style	Operating System
TCtrl00.ocx	ProCounter	ISA	Manual CMM	95/98
TCtrl01.ocx	Tech80	ISA	Manual CMM	95/98
TCtrl02.ocx	ProCounter II ^(see Note 1)	USB	Manual CMM	98/2K/XP
TCtrl03.ocx	Heidenhain VRZ-xxx	RS-232	Manual CMM	95/98/2K/XP
TCtrl04.ocx	PMAC 1	RS-232	LCD Joystick	95/98
TCtrl05.ocx	PMAC 1 / Mini-PMAC	ISA	LCD Joystick	98/2K/XP
TCtrl06.ocx	PMAC 2	ISA	LCD Joystick	95/98
TCtrl07.ocx	PMAC 1	RS-232	Game Port Joystick	95/98/2K/XP
TCtrl08.ocx	PMAC 1 / Mini-PMAC	ISA	Game Port Joystick	95/98/2K/XP
TCtrl09.ocx	PMAC 2 - ISA	ISA	Game Port Joystick	95/98/2K/XP
TCtrl10.ocx	PMAC 1	RS-232	USB Joystick	95/98/2K/XP
TCtrl11.ocx	PMAC 1 / Mini-PMAC	ISA	USB Joystick	95/98/2K/XP
TCtrl12.ocx	PMAC 2	ISA	USB Joystick	95/98/2K/XP
TCtrl13.ocx	PC104 PMAC	USB	USB / GP Joystick ^(see note 3)	98/2K/XP
TCtrl17.ocx	PMAC 1 ^(see note 2)	RS-232	LCD Joystick	98/2K/XP
TCtrl18.ocx	PMAC 2	PCI	LCD Joystick	98/2K/XP

Note 1: The ProCounter II, USB CMM Interface requires a separate installation of USB drivers, see *Install USB Drivers*.

Note 2: Requires new libraries - replaces the old TCtrl04.ocx on CD under Drivers folder- requires PMAC code changes for field updates.

Note 3: Supports both USB and Gameport Joystick. Requires PMAC code changes for field updates.

Installing the Microsoft DirectX

Geomet requires that DirectX support is installed in your Windows operating system. DirectX is a multi media extension to Windows 98, Windows XP and Windows 2000. The Geomet installation will automatically install the proper version of DirectX if required.

Installing Adobe Acrobat Reader

The Geomet On Line Help files are created in the Adobe pdf (Portable Document Format). To view these files, it is required that Adobe Acrobat Reader is installed on your system.

To install the Reader, open the Geomet Installation CD and navigate to the folder ACROREAD, open the Installers folder. The installation program is named "AdbRdr60_enu_full.exe". Launch this program and follow the installation instructions. Another method to launch the installer can be done using the "Start->Run" Windows program. Enter the full path and program name as shown in figure 8. If your CD drive is not "D:", substitute the correct drive letter. Once the program has been installed, launch Acrobat Reader and follow the instruction on using the Reader. Once you answer the questions, the Reader will now be ready for use by Geomet and other programs.




figure 8, Adobe Acrobat Reader Installer

Installing the ProCounter II USB Interface

The Helmel designed ProCounter II CMM Interface requires installing device drivers to operate correctly. The ProCounter II is designed to be recognized by the computer when it is plugged into the USB port. NOTE: when performing an upgrade to an existing installation of Geomet, the drivers will be retained and the installation of the ProCounter II drivers will not be necessary.

When the computer identifies that a new USB device has been plugged in for the first time, the Device Driver Wizard will start to assist you in installing the drivers.

Step 1 - Identifying a New Device

The first page of the Wizard acknowledges that a new USB device has been plugged in. The Wizard should find the device and show the name Helmel ProCounter Interface. Select <Next> to begin.

Step 2 - Specify Driver Location

On this page you will select a location which the Wizard will look into to locate the correct driver. Insert the Geomet Installation CD and wait until the CD spins up. Place a check next to specify a location. You can type in the location or use the <Browse> feature. To type in the location, enter D:\Drivers\ProCounterII and press <Next>. NOTE: substitute the correct CD drive letter if it is not D:.

Step 3 - Installing the Driver

The Wizard will now install and register the driver for the ProCounter II interface.

Installing the Rainbow Sentinel Driver

Geomet requires that a separate driver be installed on Windows XP and Windows 2000 operating system. This driver is for security and is not part of the normal Geomet Installer. If you are upgrading Geomet, this step is not required.

Step 1- Locate the Sentinel Installer

The setup program can be found on the Geomet Installation CD. Open the folder Driver, then open the folder SPRO. Locate then launch the program SETUPX86.EXE.

Step 2 - Start the Installer.

When SETUPX86.EXE is launched, a small dialog will appear with drop down menu Functions. Select Install Sentinel Driver from the functions available. You will be prompted with a file location tool from which you should accept the default path and press <Ok>. The installer will update your XP or 2000 system with the Sentinel driver. You will be prompted to restart your system to complete the installation process.

Geomet on the Web

Before you start using your Geomet System, we ask that you take a few minutes to review the dedicated Geomet web site which can be found at:

www.geomet-cmm-software.com

The Geomet web site is dedicated to supporting your needs by providing the latest help pages, upgrades and news.

All help topics can be found by accessing the KnowledgeBase pages. Within these pages you will find help on many topics and features found in Geomet. Use the Search page to locate all pages that provide support for a specific topic.

Through the Geomet web site you can keep current with the latest changes to Geomet. We are publishing updates to Geomet up to 4 times per month. Upgrading Geomet is available to all new system sales based on the following schedule:

- Geomet 301 1 Year
- Geomet 101 1 Year
- Geomet Junior 90 Days

Upgrades are free to all Software Service Contract holders or available for purchase.

We suggest that the CMM be placed on line and have access to the Internet. Through Geomet, there exists a direct link to the help pages located on the web site. For example, if you are measuring a circle, press the WebHelp key (minus on the upper row of the keyboard) and Geomet will connect to the KnowledgeBase and display help for the circle.

In the Help menu, you will find direct-to-web access for several help topics. These range from support feature such as submitting suggestions to sharing ideas through the use of the Geomet Forum.

